

ECAT-1000 Version Info

} **01.18.2012**

Firmware

- Chillgard V2.400 release
- A.O. Smith V2.300 release
- Added A.O. Smith AIN and PDNP drivers
- Added support for different types of scaling for the concentration values including new % units in Chillgard
- Added support for more gas types in Chillgard

User's manual version

- 10756 January 15, 2012

} **08.15.2011**

Firmware

- V2.300 release
- Added DMX-512 Master and Slave drivers
- Added M-Bus Master driver
- Added function code 05 (Force Single Coil) support to Modbus Master driver
- Increased Service Object memory usage

User's manual version

- 10757 August 15, 2011

} **02.01.2011**

Firmware

- V2.200 release.
- Added MSA Chillgard driver.
- Added Metasys N2 Master driver
- Added Siemens FLN driver.
- Added TCS BasyS driver.
- Fixed Modbus Master bug when Floating Point is checked and multiplier is 1, the value is now correctly converted as a floating point number.
- Improved accuracy of Modbus multiplier scaling.
- Updated Metasys Slave driver so that it won't reset the object configuration upon receiving the "F" command.
- Fixed Modbus Slave remap object issues.
- Added network timeout feature to EtherCAT protocol.

User's manual version

- 10757 February 1, 2011

} **03.01.2010**

Firmware

- V2.100 release.
- Added Sullair master driver.
- Added Modbus sniffer driver.
- Added Enron/Daniel 32-bit Modbus extension to Modbus master and slave drivers.
- In Modbus RTU slave driver, holding registers and input registers can now be remapped independently, and can have multipliers applied.
- Decreased object memory usage for BACnet objects in BACnet MS/TP server driver.
- BACnet MS/TP client driver now sends "Who-Is" for all configured destination devices on startup, not just statically-bound ones.
- Improved efficiency of service object handling in BACnet MS/TP client driver.
- Fixed "Poll-For-Master to self" bug in BACnet MS/TP drivers.
- Fixed "multiply by 1 rounding" issues.

User's manual version

- 10757 March 1, 2010

} **11.10.2009**

Firmware

- V2.000 initial release.

User's manual version

- 10757 October 30, 2009